

Example

Capture - Camera

by:	Greg Haynes
published:	here
description:	change Capture camera via macro
remarks:	

Remarks

- unfortunately until now it is only possible to switch between the predefined camera positions (front/up/left/right)

[capture](#), [haze](#), [settings](#)

functions

- [Visualiser.Capture.UpdatePosition](#)

affected properties

Code

[capturecamera.xml](#)

```
<?xml version="1.0" encoding="utf-8"?>
<avolites.macros>

    <!-- Capture Camera, Alex del Bondio - April 2019 -->
    <macro id="adb.Macros.Capture.TopView" name="Capture Top View">
        <sequence>
            <step>Visualiser.Capture.UpdatePosition(Windows.Visualiser.Capture.Came
raPositions, Windows.Visualiser.Capture.SelectedCamera,
CaptureCameraPositions.GetPresetPosition(Math.ToEnum("Avolites.Titan.Co
ntrollers.Console",
"Avolites.Titan.Controllers.Console.CaptureVisualiser.CaptureCameraPres
etPosition", "TopView"))</step>
        </sequence>
    </macro>
    <macro id="adb.Macros.Capture.FrontView" name="Capture Front View">
        <sequence>
            <step>Visualiser.Capture.UpdatePosition(Windows.Visualiser.Capture.Came
raPositions, Windows.Visualiser.Capture.SelectedCamera,
CaptureCameraPositions.GetPresetPosition(Math.ToEnum("Avolites.Titan.Co
ntrollers.Console",
"Avolites.Titan.Controllers.Console.CaptureVisualiser.CaptureCameraPres
etPosition", "FrontView"))</step>
        </sequence>
    </macro>
```

```
etPosition", "FrontView")))</step>
    </sequence>
</macro>
<macro id="adb.Macros.Capture.RightSideView" name="Capture Right
View">
    <sequence>
<step>Visualiser.Capture.UpdatePosition(Windows.Visualiser.Capture.Came
raPositions, Windows.Visualiser.Capture.SelectedCamera,
CaptureCameraPositions.GetPresetPosition(Math.ToEnum("Avolites.Titan.Co
ntrollers.Console",
"Avolites.Titan.Controllers.Console.CaptureVisualiser.CaptureCameraPres
etPosition", "RightSideView")))</step>
    </sequence>
</macro>
<macro id="adb.Macros.Capture.LeftSideView" name="Capture Left
View">
    <sequence>
<step>Visualiser.Capture.UpdatePosition(Windows.Visualiser.Capture.Came
raPositions, Windows.Visualiser.Capture.SelectedCamera,
CaptureCameraPositions.GetPresetPosition(Math.ToEnum("Avolites.Titan.Co
ntrollers.Console",
"Avolites.Titan.Controllers.Console.CaptureVisualiser.CaptureCameraPres
etPosition", "LeftSideView")))</step>
    </sequence>
</macro>

</avolites.macros>
```

Explanation

This explains the functional steps within the sequence. For all the other XML details please refer to [Formats and syntax](#)

How to use it

- make this macro available

From:
<https://avosupport.de/wiki/> - AVOSUPPORT

Permanent link:
<https://avosupport.de/wiki/macros/example/captureatmosphere?rev=1556468725>



Last update: **2019/04/28 16:25**